

Rapid Annotator User Guide

The Red Hen Rapid Annotator is designed to enable you to go through a large number of images in a very short period of time and to get you started with minimal training. Nonetheless, it is vital that you read carefully through this document.

Experimenter section

Initially you will be an annotator. You can make a request to admin to make you either an experimenter or an admin.

Basic Setup

In order to prepare a dataset for the *Red Hen Rapid Annotator*, you need to go through three simple steps: data preparation, parameter setting and user notification.

Data Preparation

The data needed for the *Red Hen Rapid Annotator* can be any of the following categories: Image, Audio, Video or Text. The allowed formats for the respective categories are: JPG, PNG or GIF.

Text : txt, html

Image : jpg, png, gif

Audio : mp3, wma, mp2, wav

Video : mov, mp4, wmv, webm

Data can be added either manually or via Spreadsheet.

MANUALLY : Chooses files and upload them.

VIA SPREADSHEET : Content of each file should be in a separate row. Don't leave any row blank in between. Start from the first row itself. Fill the following detail in each respective column

1. Name
2. Content - for text plain text, for image / video / audio - url to the location where the actual data is.
3. Caption

Once files are uploaded you can **modify name or caption** of files by double clicking on the them in add_experiment page.

Adding Annotation Levels & Labels : Click on Add labels in the main add_experiment page. Click Add Annotation Level to add a new annotation level for example **height**. You can add multiple labels like (**tall, short, medium**) to an annotation level.

Hint: Use an additional label such as problem so your annotators can skip an item where they feel they would have to ask you first. Like this, you can later take a look at the problematic cases in detail.

You have freedom to bind any key with respective labels. Although if you leave it empty any default key binding will be made dynamically. You can also control in the order in which the annotation levels are displayed by providing annotation level number.

You can see results in the Results page by clicking on Results Page button in the main add_experiment page.

You can **add annotator / owner** to your experiment either in main add_experiment page or in its settings page. You can **assign** any number of files with a specific annotator from settings page. You can also **delete** the experiment from there.

Annotator section

You can see all the experiments assigned to you in Experiment to Annotate tab of your home page.

The screenshot displays the Rapid Annotator web application. At the top, there is a navigation bar with a red chicken icon, the text "Rapid Annotator", and links for "Home" and "My Profile". Below this, a breadcrumb trail shows "Home > Annotate Experiment". The main content area features a video player on the left, currently showing a scene from a restaurant with the title "Food Lounge". To the right of the video player, there is a section titled "Speed of the video" with the instruction "Tell the approximate speed of the video shown." Below this, a "Key Bindings" section lists: "f : fast", "v : Very fast", "s : slow", "t : still", and "d : flashed". At the bottom of this section are five buttons: "fast", "Very fast", "slow", "still", and "flashed". Above the video player, there is a "V" icon and a "Turn off looping" button. The video player itself has a progress bar showing "2:41 / 3:38" and standard playback controls.

2

On clicking on any experiment you see the valid labels and the keys assigned to them. so in this case if the speed of the video clip is fast you press f, if it is not playing then still and so on. If you prefer to work with a mouse or a touch-device such as a tablet computer, you can also click the buttons at the top of the page. As soon as you press the key or the button, your annotation is saved to the server and the next annotation level(if any) is loaded. On all levels for a picture are annotated then next file is rendered for annotation. It is always possible to stop the annotation process and come back later. You can also **UNDO** any annotation that you wish to. But once all the files are annotated there is no going back.

Turn off / on Looping feature enables you to turn on / off looping of audio - video clips.